

Activating the PROFINET Master Simulator

The software can be activated with or without Internet access. Both procedures are described here.

1 Computer with Internet access

1. Follow the download link in the software license document, enter the coupon code in the assigned box, then click on **Next**.



PROFINET™ Master Simulator

Please enter your coupon code provided by HMS to commence your software download.

(Please note that the software will be installed and licensed to the machine you are currently using to complete this download)

► [Click here to register the software for a computer without Internet access](#)

Instructions: Download and installation procedure 

Download software

To download purchased software, please enter your coupon code.

Coupon code

Next

2. Read and accept the terms and conditions and confirm with **Next**.

Licensed Software

☒ I have read and agree to the General Terms and Conditions and the Supplementary Clause: Extended Retention of Title.

☒ I have read and agree to the End User License Agreement/Software License Agreement.


☒ I hereby confirm that I am acting as an entrepreneur within the meaning of § 14 BGB (German Civil Code) and not as a consumer in the meaning of § 13 BGB (German Civil Code).

Next











3. Now the acquired software will be available as a zip file for download:

Download software

The following downloads are available:

	Download: 024710 PROFINET Master Simulator 1.0.1.42 Downloads: 2	76.5 MB
---	---	---------

4. Save and unpack the software on the computer.
5. Double-click on “Setup.exe” to start the installation.

Name	Type
 Default.licstor	License Manager PROFINE...
 PackageInfo.ini	Configuration settings
 SetupCfg.cab	Cabinet File
 AddiData.cab	Cabinet File
 Backgrnd.cab	Cabinet File
 Setup.exe	Application
 WinPcap_4_1_3.exe	Application
 vcredist_x86.exe	Application
 pniomastersimulator.msi	Windows Installer Package
 dotNetFx40_Full_x86_x64.exe	Application

6. After installing and starting the software a message will appear:
No valid license found. Would you like to add a new license?
Click on **OK** and enter your license data.

Add License

Add new license

Please enter your license data

First Name

Last Name

Company

E-Mail

Please choose whether you want to redeem a coupon code online or already have a license key:

☒ Coupon code

Note: This requires Internet access. If you do not have Internet access on this computer you can visit our activation website on another computer to redeem your coupon code and receive a license key. You may need the following hardware ID.

Web registration: <http://licensing.bihl-wiedemann.de>

Your hardware ID: B096 7BE6 C677 88FE A953 AEA4

☐ License key

Next > Cancel Help

7. If the license information has been added successfully you will receive an e-mail with the registered license data.

If licensing over the Internet fails:

If you fail to acquire a license over the Internet, the firewall on your network may be filtering the traffic required by the licensing server:


- Requests are done via HTTP POST over TCP port 80 as JSON objects.
- Requests are sent to licensing.bihl-wiedemann.de.
- Also check whether additional personal filters are set to objects.

Contact your network administrator for assistance if in doubt.

If the firewall settings cannot be changed to allow the required traffic for licensing over the Internet, follow the procedure for activating the software on a computer without Internet access.

2 Computer without Internet access

1. Download the software using a computer with Internet access as described above (steps 1 to 3).
2. Copy the software archive to the computer without Internet access.
3. Unpack the software archive on the computer without Internet access and run the installer by double-clicking on **Setup.exe**.
4. Start the software. Write down the **hardware ID** which is shown in the Add License window. Do not close the window, as you will enter the license key here later.



Add License

Add new license

Please enter your license data

First Name

Last Name

Company

E-Mail

Please choose whether you want to redeem a coupon code online or already have a license key:

☒ Coupon code

Note: This requires Internet access. If you do not have Internet access on this computer you can visit our activation website on another computer to redeem your coupon code and receive a license key. You may need the following hardware ID.

Web registration: <http://licensing.bihl-wiedemann.de>

Your hardware ID: **B096 7BE6 C677 88FE A953 AEA4**

☐ License key

Next > Cancel Help

5. On the computer with Internet access, go back to the registration page and click on the link “Click here to register the software for a computer without Internet access”.




PROFINET™ Master Simulator

Please enter your coupon code provided by HMS to commence your software download.

(Please note that the software will be installed and licensed to the machine you are currently using to complete this download)



► Click here to register the software for a computer without Internet access

Instructions: Download and installation procedure 

6. In the **Software licensing** form, fill in the required fields including the hardware ID from the computer without Internet, then click on **Next**.

Software licensing


Coupon code *	<input type="text"/>
First Name *	<input type="text"/>
Last Name *	<input type="text"/>
Company *	<input type="text"/>
E-mail *	<input type="text"/>
Hardware ID *	<input type="text"/>

* Mandatory fields

Next

7. A license key will now be generated. Click on the **License Key** link to download the key file.

Software licensing

 **License key:**

8HN2W SWQKY K3P46 LGN78 KHQ9C2

First Name	Niklas
Last Name	Selander
Company	HMS
E-mail	nia@hms.se
Hardware ID	B0967BE6C67788FEA953AEA4

Download license key file to be imported into License Manager: [License Key](#)

8. On the computer without Internet access, enter **exactly** the same license data in the **Add License** form as you did in the **Software licensing** form on the other computer.

IMPORTANT: The license data must be identical in every way, including spaces, use of upper/lower case, etc.

Enter the generated license key in the **License key** field, then click on **Next**.

Add License

Add new license

Please enter your license data

First Name: Niklas

Last Name: Selander

Company: HMS

E-Mail: nia@hms.se

Please choose whether you want to redeem a coupon code online or already have a license key:

☐ Coupon code

Note: This requires Internet access. If you do not have Internet access on this computer you can visit our activation website on another computer to redeem your coupon code and receive a license key. You may need the following hardware ID.

Web registration: <http://licensing.bihl-wiedemann.de>

Your hardware ID: B096 7BE6 C677 88FE A953 AEA4

☒ License key

8HN2W SWQKY K3P46 LGN78 KHQ9C2

Next > Cancel Help

9. Copy the downloaded license key file to the computer without Internet access, then start the **License Manager** and click on **Import** to import the key.

